

APPENDIX 6

Wisconsin Smoke Management Plan: Best Management Practices for Prescribed Burns

WISCONSIN SMOKE MANAGEMENT PLAN: BEST MANAGEMENT PRACTICES FOR PRESCRIBED BURNS

Table of Contents

INTRODUCTION	1
Use of Prescribed Fire for Ecosystem Management in Wisconsin	1
Background	2
Purpose	2
Organizations That May Wish to Sign on to the Smoke Management Plan	3
SMOKE MANAGEMENT BEST MANAGEMENT PRACTICE GUIDELINES:	
Burn Permitting	4
Burn Planning	5
Burn Plan Elements	5
Evaluating Smoke Dispersion and Sensitive Receptor Sites	5
Smoke Dispersion Forecasts	7
Actions to Minimize Fire Emissions.....	7
Transportation & Utilities	8
Road Impacts	8
Railway Impacts	9
Air Traffic Impacts	9
Utility Impacts	9
Outreach, Enforcement, & Evaluation	10
Public Education and Awareness	10
Record-keeping and Enforcement	10
Optional Air Quality Protection	10
Program Evaluation	10
GLOSSARY	11
LITERATURE CITED	14

Appendices

A: Principle Contacts for Wisconsin Smoke Management Plan	15
B: Basis for Developing Smoke Management Best Management Practices	16
C: Smoke Production and Dispersion	17
D: Guideline for Use of the Ventilation Index	19

INTRODUCTION

Use of Prescribed Fire for Ecosystem Management in Wisconsin

Many of the vegetation cover types within the state evolved with fire as the natural process for maintaining plant community structure and composition (Curtis, 1959). For thousands of years, vast, sweeping wildfires occurred across the landscape; either through lightning strikes or through Native populations as they prepared settlements and/or attracted game species to the area (Dorney, 1981; Dorney & Dorney, 1989). Because frequent fire played a significant and extensive role in the development of much of Wisconsin's native plant communities, many plant and animal species now depend on fire for their continued existence.

The practice of mimicking fire's natural ecosystem benefits in a specific area under controlled settings is known as prescribed fire. Prescribed fire is an important tool in Wisconsin for restoring and maintaining fire-dependent ecosystems, providing wildlife habitat, reducing hazardous fuel buildups, and meeting silvicultural and other needs. Vegetation types ranging from grasslands and prairie plantings, to wetlands, savannas, conifer and hardwood forests, brush lands and agricultural fields are all treated with prescribed fire. Prescribed fire, also known as open burning, is often the most cost-effective method for landscape-scale land treatments. Piled slash is also burned throughout the year for cover type conversion, site preparation, and to mitigate insect- and disease-related problems such as oak wilt.

The decline of naturally-occurring fires over the past 100 years has contributed to the loss of acreage and of these ecosystems, and a decrease in the integrity of the remaining acreage. Use of prescribed fire has been intermittent since the post-logging era wildland fires, and lightning-caused fires are often quickly suppressed before they can provide any major benefit to the plant community. The decline in quality of various fire-dependent ecosystems such as savannas, oak and pine barrens, grasslands, and wetlands, are a direct effect of removing this disturbance from the landscape. To restore and maintain the integrity of these systems, it is crucial that prescribed fire be allowed to occur, where and when it is necessary.

In summary, the main reasons to use prescribed fire include:

- Wildlife habitat improvement and maintenance
- Site preparation and seed production
- Ecosystem management and restoration
- Maintenance of biological diversity
- Restoration of fire as a natural process
- Control of insect and disease
- Fuel reduction, including hazardous fuels
- Minimizing the potential for significant air quality impacts from wildfire
- The training of fire personnel resources
- Testing of fire suppression equipment and suppression techniques.

The use of prescribed fire presents the need to weigh the ecological benefit of this practice vs. the impact of increased emissions from current and accelerated prescribed burning programs. To have a successful and sustained prescribed burn program, it involves the careful consideration of and application of smoke management techniques to minimize the impact of emissions, while still meeting the ecological needs during the prescribed burn.

Background

This Smoke Management Plan (SMP) has been developed to minimize those potential air quality impacts while optimizing the opportunity to use prescribed fire as a land management tool. In 2005, several public and private land management agencies and organizations agreed to develop and implement smoke management best management practices to mitigate potential air quality impacts from prescribed fire. In general, agencies and organizations in Wisconsin that conduct prescribed burns prepare site specific individual burn plans. State law and/or local ordinances may require burn permits for “open burning.” Currently most prescribed fire plans include provisions that address the effects of smoke to varying degrees. This SMP will begin a formal effort to minimize impacts of smoke produced from prescribed burns in Wisconsin.

The EPA Exceptional Events Rule published on September 30, 2016 states that all wildfires will be considered as natural events and will not be counted in determining an areas attainment or non-attainment status. The impact of prescribed fires may be discounted if the burn was conducted under a certified Smoke Management Plan or the burner was using basic smoke management practices (as defined by the applicable air quality regulatory agency).

The Division of Forestry of the Wisconsin Department of Natural Resources (DNR) serve as the central authority for the State’s SMP. The SMP guidelines will become effective when the DNR certifies in writing to the U.S. Environmental Protection Agency (EPA) that a SMP has been adopted and implemented.

Purpose

These smoke management best management practices are a set of guidelines and procedures that are followed by signatory organizations to reduce the adverse effects of smoke from prescribed fires. The goal of the Wisconsin SMP is to prevent violations of the federal fine particles standard (PM_{2,5}) and minimize adverse effects including:

- Health effects from smoke inhalation
 - Premature death
 - Decreased lung function
 - Increased asthma attacks and chronic bronchitis
 - Acute respiratory symptoms
 - Respiratory- and cardiopulmonary-related hospital admissions
 - Increased work and school absences
- Visibility-related travel hazards
 - Aircraft
 - Highways
 - Rail
- Electric utility hazards
- Violations of an ambient air quality standard
- Decreased visibility in scenic vistas

Organizations that May Wish to Sign on to the Smoke Management Plan

In Wisconsin, a variety of federal, state, county, and non-profit conservation groups, as well as numerous private prescribed burn contractors all use fire to accomplish goals and objectives ranging from ecosystem management to fuels reduction (Table 1). USDA conservation programs (e.g., Conservation Reserve Program, Wildlife Habitat Incentives Program) offered through the Farm Service Agency and Natural Resources Conservation Service (NRCS) place an emphasis on prescribed fire, making the increased use of prescribed fire in the private sector a general trend. Any organization that actively conducts prescribed burns and can adequately encourage and enforce the SMP's Best Management Practices is eligible to become a signatory on the Smoke Management Plan. For further information on the basis for developing the Smoke Management Plan in Wisconsin, please see Appendix B.

This SMP is an evolving document and will undergo ongoing evaluation using stakeholder input. The SMP document will be reviewed together by the principle contacts of the signatories every five years and amended as necessary to achieve the purpose of the SMP and incorporate changes in regulations, policies and advances in technology.

Agency/Organization Prescribed Burn Annual Acreages									
Agency	2002	2003	2004	2005	2006	2007	2008	2009	Total Acres
USF&WS	5677	6928	5996	9345	7681	9601	7982	7359	60569
WIDNR	18750	19750	19500	20000	19000	27000	21550	21330	166880
USFS	586	2108	1259	1045	3211	1201	3450	775	13635
TNC	818	636	609	418	895	596	375	550	4897
Pheasants Forever	100	150	295	200	850	870	500	775	13635
NRCS		40	30	350	830	1015	3826	7010	13101
DoD Fort McCoy	5121	5583	5627	5270	5731	4856	3130	550	4897
BIA			400	630	720	100	350	1258	3458
WDOT		160	280	80	120	80	20	30	770
Mississippi Valley Conservancy					129	56	22	60	267
MITW		140	11	371	280	521	514	850	2936
Total Acres	31052	35335	33727	37629	39198	45760	41677	48157	319087

Table 1: Agency/organization prescribed burn annual acreages

BEST MANAGEMENT PRACTICE GUIDELINES:
BURN PERMITTING

Signing organizations agree to follow the SMP best management practice guidelines below as part of their day-of-burn decision-making.

The DNR Division of Forestry is responsible for issuing permits for open burning in organized protection areas, outside of incorporated cities or villages in Wisconsin (Figure 1), for forest fire protection purposes. In cooperative protection areas, town chairpersons are responsible for issuing permits for open burning for forest fire protection purposes. This authority is stated in [Wisconsin State Statute Chapter 26](#) and associated administrative rules.

The DNR issues written permits for open burning of vegetation (see Figure 1 below). A permit is not required when the ground is covered with snow. Permitting of open burning is also administered locally when municipalities or townships have local ordinances more restrictive than the state rules.

[Wisconsin Administrative Code, NR 429.04\(1\)](#) prohibits open burning with certain exceptions. One of those exceptions is backfires to control forest fires or fires set for forest or wildlife habitat management with the approval of the DNR where no reasonable alternative is available. Factors in considering the reasonableness of alternatives may include: 1) costs of other alternatives, 2) availability of other alternatives, or 3) effectiveness of each of the other alternatives in comparison to a prescribed burn in achieving the land management objectives. In addition, [NR 429.04\(2\)](#) specifies that all allowed open burning shall be conducted in a safe, pollution-free manner, when wind and weather conditions will minimize adverse effects and in conformance with local and state fire protection regulations.

Historically, federal agencies in Wisconsin have complied with state burning regulations. The SMP is a formal agreement among signatory agencies for following state burning regulations for the purposes of future smoke-related emission and impact reduction.

DNR FOREST FIRE PROTECTION




Figure 1: Forest fire protection and co-op areas in Wisconsin

BEST MANAGEMENT PRACTICE GUIDELINES: BURN PLANNING

Signing organizations agree to follow the SMP best management practice guidelines below as part of their burn plan content.

Burn Plan Elements

All signatories to this SMP agree to have burn plans that incorporate the elements listed below. They should be on file at agency or organization offices and are available upon request. Prescribed burn plans will include the following elements at a minimum:

- Location and legal description (Town, Range, Section and quarter-quarter section) of the area to be treated, including ownership
- Personnel and/or certified prescribed Burn Boss responsible for managing the fire
- Type of vegetation or fuel model (utilizing the National Fire Behavior Prediction System) to be burned
- Area in acres to be burned
- Amount of fuel to be consumed*
- Fire prescription including smoke management components and ventilation index limits
- Criteria the fire manager will use for making go/no-go burn decisions
- Safety and contingency plans

**As an example, if burning in a Fuel Model 6 (brush fuel type), and the objective is to reduce 75% of the woody vegetation, this can be calculated by multiplying average fuel present (6 tons/acre) by 75%. This results in amount of fuel to be consumed equaling 4-1/2 tons/acre. Fuel loading assumptions for the standard 13 fuel models can be found within the [Aids to Determining Fuel Models for Estimating Fire Behavior](#) (Anderson, 1982).*

Evaluating Smoke Dispersion and Sensitive Receptor Sites

Prescribed burn plans should identify and evaluate potential smoke impacts on sensitive receptors. Fires should be timed to minimize exposure of sensitive populations (those that smoke may present particular health risks). For more information on smoke production and dispersion, please see Appendix C.

There are 5 steps to address sensitive receptor sites and smoke dispersion:

- Identify and list sensitive receptor sites
- Specify the requirements for smoke dispersal at sensitive receptor sites
- Check for [Air Quality Advisories](#) and elevated AQI levels
- Notify affected populations and authorities
- Identify monitoring plans for sensitive receptor sites

These steps are further described below.

1. Identify and list sensitive receptor sites

Sensitive receptor sites are usually defined as locations where human populations tend to concentrate and where smoke could impact the health of those populations or significantly impact visibility that may be detrimental to health or the enjoyment of scenic qualities of the landscape. These may be residential concentrations in the form of towns or cities, or locations where people tend to gather in groups such as parks and schools. Areas where citizens can be especially sensitive to smoke include hospitals, schools, and retirement facilities. Travel routes such as highways may be labeled as sensitive receptor sites where smoke can be a factor in potential motor vehicle accidents. Particular areas along highways or other locations may be more prone to being declared sensitive receptor sites because of topographic and microclimate features.

2. Specify the requirements for smoke dispersal at sensitive receptor sites

The plan should identify the distance and direction from the burn site to local sensitive receptor areas where appropriate. Fire prescriptions will specify minimum requirements for the atmospheric capacity for smoke dispersal such as minimum surface and upper level wind speeds, desired wind direction, minimum mixing height, and dispersion index. Utilize the Ventilation Index explained in Appendix D for minimum requirements.

3. Check for Air Quality Advisories

The Burn Boss or prescribed fire manager responsible for a proposed prescribed burn has the responsibility to ensure that there is no air quality advisory in effect for the county or counties affected by smoke dispersal on the day that the prescribed burn occurs. Check the Air Quality Index (AQI) for the area of the burn and downwind impact zone on the [DNR website](#) or the [AirNow website](#) (both post air quality advisories). When AQI values are orange (unhealthy for sensitive groups) or above in the area where the burn unit is located, or in the downwind smoke impact zone, further evaluation and consideration should be exercised. Air Quality Advisory information can also be delivered by [email alerts](#), which staff can sign up for,

In the event of an air quality advisory, signatories to this SMP agree to cancel all open burning related to prescribed fire use for the applicable county or counties while the advisory remains in effect.

4. Notify affected populations and authorities

The burn plan should identify actions that will be taken to notify populations and authorities at sensitive receptors, including those in adjacent jurisdictions, prior to the fire. The plan should also identify contingency recommendations that should be taken during a fire to reduce the exposure of people at sensitive receptors if smoke intrusions occur.

Recommendations below are from the National Wildfire Coordinating Group's Smoke Management Techniques Course (RX-410):

- Notify sensitive receptors and the DNR Air Management Program as soon as possible when conditions change
- Place field observers at sensitive receptors to monitor smoke conditions
- Work with local health agencies and DNR Air Management Program (issues air quality health advisories)
- Relocate smoke-sensitive people
- Terminate project
- Accelerate completion of project

5. Identify monitoring plans for sensitive receptor sites

The plan should identify how the effects of the fire on air quality at sensitive receptor areas should be monitored. The extent of the monitoring plan should match the size of the fire, fuel loading and consider the proximity to smoke sensitive areas. For small, or short duration fires (such as those in grass or leaf litter), visual monitoring of the directions of the smoke plume and monitoring nuisance complaints by the public may be sufficient. Other monitoring techniques include posting personnel at sensitive receptors to identify smoke intrusions and continued tracking of meteorological conditions during the fire. For fires in fuels with longer duration burning (such as timber litter or slash), and which are expected to last more than one day, [locating real-time PM monitors](#) at sensitive receptors may be warranted to facilitate timely response to smoke impacts.

Smoke Dispersion Forecasts

The National Weather Service (NWS) forecast offices in Green Bay, Sullivan, LaCrosse, Duluth, MN, and Minneapolis, MN provide twice daily fire weather forecasts every day during the fire season (generally April 1st to November 1st). The fire weather forecasts issued by the respective NWS offices, at 0700 and again by 1500, include projected smoke management information. The Fire Weather Annual Operating Plan (FWAOP), available at the forecast offices or most agency dispatch or coordination centers, provides extensive forecast information.

To ensure optimum dispersal of smoke emissions during prescribed burns, the mixing height should be deep enough and have sufficient transport wind speed to ensure the dilution and dispersal of emission concentrations. The ventilation index multiplies mixing height (measured in feet) and transport wind speed (measured in knots per hour) to produce an index that expresses the ability of the atmosphere to disperse emissions. This dispersion information is included as part of the daily fire weather forecast. It describes the mixing height, transport wind speed and ventilation index for the peak or low conditions during the forecast period. State and federal agency prescribed fire managers who plan ignitions at other than the time listed on the forecast may request dispersion/ventilation criteria as part of a spot weather forecast from the NWS. At

this time, a spot weather forecast from the NWS is not available to the private sector. For more information on the ventilation index, refer to Appendix D.

Actions to Minimize Fire Emissions

The burn plan should document the steps to be taken prior to, during, and after the burn to reduce air emissions. This could include, but may not be limited to, any of the following measures stated in the [Smoke Management Guide for Prescribed Fire](#) (NWCG, 2018):

- Minimize the area burned; reduce the acreage burned per burning period or use non-fire treatments.
- Reduce the fuel loading in the area to be burned by mechanical means, or by using frequent, low intensity burns to gradually reduce fuels.
- Reduce the amount of fuel consumed by the fire by burning when large non-target fuel moistures and duff moistures are higher.
- Minimize emissions per ton of fuel consumed, by using mass ignition techniques, using backing fires, increasing combustion efficiency and performing rapid and complete mop-up.
- Pre-treat heavy fuels or use firing techniques that exclude them from the burn.
- Minimize potential smoke impacts on sensitive receptors

SMOKE MANAGEMENT BEST MANAGEMENT PRACTICE GUIDELINES: **TRANSPORTATION & UTILITIES**

Signing organizations agree to follow the SMP best management practice guidelines below as part of their mitigation strategy for transportation and utility infrastructure.

Road Impacts

The Wisconsin Department of Transportation (WDOT) is responsible for maintaining the state and federal highways within Wisconsin. If a prescribed burn is being planned within a WDOT right-of-way (ROW) by another state or federal land management agency, organization or private landowner, a DOT permit may be required. Planning for smoke management adjacent to state and federal highways begins with contacting the local WDOT Regional Office to determine if a DOT permit is required. Each WDOT Regional Office has an [individual contact for obtaining right-of-way permits](#).

The following documents will be submitted to the WDOT Regional Right of Way permit contact:

1. [Application/Permit to Work on Highway Right-Of-Way](#) (WDOT Form DT 1812)
2. The approved burn plan

Processing time for permit approval is up to 30 days and is intended for non-emergency activities. The approval of an annual permit rather than an individual permit may be desirable to accommodate flexibility in the time range to complete multiple burns adjacent to highways planned by state and federal land managers.

The thresholds for pre-planning the distance of a burn from travel routes should be determined on a site-by-site basis. Property ownership, rural vs. urban environment, average daily traffic (ADT) and the justification for burning within the vegetated ROW should be evaluated and addressed within the burn plan.

Participation in the WDOT ROW permit process as described above should assure that the Burn Boss/Fire Manager receives specific information on the required signage and its proper placement within the ROW. The WDOT brochure [Work Zone Safety: Guidelines for Construction, Maintenance, & Utility Operations](#) is an excellent reference. The use of electronically programmable signs for smoke warning and speed reduction is an option. The responsibility for providing standard signs or renting the programmable signs lies with the agency or organization conducting the prescribed burn. Traffic control devices placed and maintained by the state, county, city or other local officials are required by Wisconsin law to conform to the [Wisconsin Manual on Uniform Traffic Control Devices](#).

For emergency situations, Burn Bosses should immediately call 911 or local law enforcement or contact the local Region WDOT Emergency Coordinator for the fastest response. The use of signage, the decision to temporarily close a state or federal highway and to reroute traffic must be coordinated with WDOT in cooperation with fire officials and law enforcement.

Responsibility for county, city, or town roads is under the jurisdiction of the local unit of government. Prescribed fire managers/Burn Bosses should contact local highway officials for the permitting process. Contact information for each [County Highway Commissioner](#) in Wisconsin is available on the WDOT website. Detailed information about all roads within the state of Wisconsin including State and Federal Routes, County roads, Town roads or others can be found at the [WDOT maps website](#).

Authority to control traffic must be coordinated with state, county, or local units of government having jurisdiction over the road. The best practice would be not to burn when it is apparent that smoke would be placed over a roadway.

Railway Impacts

Contact the emergency management representative for the specific railroad effected. These representatives should have firsthand knowledge of their internal processes for emergency response to smoke and the timing of rail activity along the rail line.

The [Official Rail Map and directory of railroads](#) is available from the WDOT public website. The *Wisconsin Rail Map, Emergency Railroad Phone Numbers* and *Required Clearances near Railroad Tracks* are just a few of the documents available to assist in planning for smoke management along railroad corridors.

Air Traffic Impacts

The coordinating agency should contact any private and/or public airport within 10 miles of the closest burn perimeter so that air traffic control is aware of the situation. Prescribed burning within 5 miles of an airport perimeter should be closely coordinated with the airport manager/owner so that the burn does not conflict with airport usage (e.g. new pilot training). The [WDOT airport website](#) can provide detailed information on airport locations and contact information on locations.

Utility Impacts

The safety of fireline personnel in relation to fire use near overhead transmission lines, where smoke, ash and incidental mist from fireline operations may contaminate the insulators on transmission structures is a consideration. Standard utility recommendations are to maintain a minimum radial distance of 35 feet between firefighters, vehicles, and transmission structures to protect firefighting personnel from this electrical hazard. Further recommendations would be to place containment lines no closer than 100 feet of and parallel to the edge of the outer most conductor.

Planning to address the direction and dispersion of smoke in these situations is critical as a heavy smoke plume on power lines may cause a conductor to ground short. Consider including any utility owner or operator that maybe impacted in the planning process. Qualified company representatives are responsible for safely adhering to all other rules pertaining to this subject matter.

SMOKE MANAGEMENT BEST MANAGEMENT PRACTICE GUIDELINES: OUTREACH, ENFORCEMENT, & EVALUATION

Signing organizations agree to follow the SMP best management practice guidelines as part of their outreach, enforcement, and evaluation strategies.

Public Education and Awareness

Agencies and organizations that conduct prescribed burns should work to establish and maintain programs to stress the use and importance of fire for ecosystem and related land management goals. Public health and safety are critical to this effort.

Record-keeping and Enforcement

Prescribed Burn Bosses should follow a pre-burn Go/No-go procedure to ensure that the burn day parameters meet the burn plan prescription, including the smoke management best management practices. Failing to follow the burn plan prescription, Burn Bosses would be subject to that organization's specific review protocols and possible disciplinary action. Agencies are encouraged to include prescribed burn personnel from other signatory agencies in any prescribed fire review. Should legal action be taken for a prescribed burn that may trigger a review, the review may be delayed or pre-empted by necessary legal considerations.

Signatory agencies should also maintain records necessary to demonstrate an Exceptional Event, per [Environmental Protection Agency Exceptional Event Rules](#). This allows the DNR to petition EPA to exclude historic exceptional event data. In 2017, the allowable time period to exclude historic data was 4 years. In addition, the DNR air monitoring contact should review data from the existing PM_{2,5} and ozone monitors in Wisconsin. Any correlations of National Ambient Air Quality Standards (NAAQS) with prescribed burns should be assessed. In the event an exceedance (PM₁₀, PM_{2,5}, or ozone) is recorded, DNR will notify the principal contacts listed in the MOA to ensure the documentation necessary to demonstrate an Exceptional Event is collated and available.

Optional Air Quality Protection

Agencies should consider opportunities to establish specific, stringent protection for those special areas requiring additional regulation in the interest of public health and safety. Recognition of these areas should be documented in site-specific burn unit plans, along with the steps to minimize impacts.

Program Evaluation

To evaluate the effectiveness of the SMP, the DNR Prescribed Fire Specialist will annually review information on acres burned by fuel type with prescribed fire. Reports of nuisance complaints or smoke intrusions should be noted and used to measure the effectiveness of this plan. Upon implementation of this plan, by January 31st of each year signatories should annually submit electronically to DNR Prescribed Fire Specialist the following:

1. Acres prescribed burned by fuel model for the previous calendar year.
2. Amount of fuel consumed, based on fuel model
3. Date of burns
4. Moisture content (if available)
5. Location and legal description of burns conducted.
6. Nuisance complaints or smoke intrusions. DNR will estimate emissions based upon stakeholder inputs for inclusion in the annual emissions report for the previous calendar year to EPA. The annual emissions report will be shared with contacts listed in this agreement.

GLOSSARY

air quality – The characteristics of the ambient air (all locations accessible to the general public) as indicated by concentrations of the six air pollutants for which national standards have been established [i.e., particulate matter (PM), sulfur dioxide (SO₂), nitrogen dioxide (NO₂), ozone (O₃), carbon monoxide (CO) and lead], and by measurement of visibility in mandatory Federal Class I areas.

Air Quality Advisory – An air quality advisory is issued when the ambient air quality in an area is unhealthy for sensitive individuals or when the air quality is expected to degrade to that level within a few hours.

ambient air – That portion of the atmosphere, external to buildings, to which the general public has access.

attainment area – A geographic area in which levels of a criteria air pollutant meet the national ambient air quality standard (NAAQS) for the pollutant. An area may have an acceptable level for one criteria air pollutant, but may have unacceptable levels for others. Thus, an area could be both attainment and non-attainment at the same time. Attainment areas are designated by EPA.

Burn Boss – Person responsible for supervising a prescribed burn from ignition through mop-up.

Class I Area – An area set aside under the Clean Air Act (CAA) to receive the most stringent protection from air quality degradation. Mandatory Class I Federal areas are (1) international parks, (2) national wilderness areas which exceed 5,000 acres in size, (3) national memorial parks which exceed 5,000 acres in size, and (4) national parks which exceed 6,000 acres and were in existence prior to the 1977 CAA Amendments. The extent of a mandatory Class I Federal area includes subsequent changes in boundaries, such as park expansions.

combustion – Burning. Many important pollutants, such as sulfur dioxide, nitrogen oxides, and particulates (PM₁₀) are combustion products, often products of the burning of fuels such as coal, oil, gas and wood

criteria air pollutants – A group of air pollutants regulated by EPA on the basis of criteria (information on health and/or environmental effects of pollution) and for which NAAQS have been established. In general, criteria air pollutants are widely distributed all over the country. They are: particulate matter (PM), carbon monoxide (CO), sulfur dioxide (SO₂), ozone (O₃), Nitrogen Oxide (NO_x) and lead (Pb).

emission – Release of pollutants into the air from a mobile source (e.g. vehicle), stationary source (e.g. industry), or area sources (e.g. gas stations, chimneys, vegetative burning). We say sources emit pollutants

fuel – Includes combustible vegetative matter such as grass, trees, shrubs, limbs, branches, duff, and stumps.

haze – Particles in the air that scatter light and degrade visibility.

monitoring (monitor) – Measurement of air pollution is referred to as monitoring. EPA, state and local agencies measure the types and amounts of pollutants in the ambient air.

National Ambient Air Quality Standards (NAAQS) – National standards for maximum acceptable concentrations of “criteria” pollutants in the ambient air. Designed to protect public health with an adequate margin of safety (primary standard), and to protect public welfare from any known or anticipated adverse effects of such pollutants (e.g., visibility impairment, soiling, materials damage, etc.) in the ambient air (secondary standard).

non-attainment area – A geographic area in which the level of a criteria air pollutant is higher than the level allowed by the federal standards. A single geographic area may have levels that are acceptable of one criteria air pollutant but unacceptable levels of one or more other criteria air pollutants; thus, an area can be both attainment and non-attainment at the same time.

nuisance smoke – Amounts of smoke in the ambient air, that interfere with a right or privilege common to members of the public, including the use or enjoyment of public or private resources.

ozone – A highly reactive gas consisting of three oxygen atoms.

particulate matter (PM) – Any airborne finely divided material mixture of very small particles that are suspended in the atmosphere, except uncombined water, which exists as a solid or liquid at standard conditions (e.g., dust, smoke, mist, fumes, or smog).

PM₁₀ – Particles with an aerodynamic diameter less than or equal to a nominal 10 micrometers (including PM_{2.5}). Concentrations in the air are measured as micrograms per cubic meter of air ($\mu\text{g}/\text{m}^3$).

PM_{2.5} – Particles with an aerodynamic diameter less than or equal to a nominal 2.5 micrometers. Concentrations in the air are measured as micrograms per cubic meter of air ($\mu\text{g}/\text{m}^3$).

prescription – Measurable criteria that guide selection of appropriate management response and actions. Prescription criteria may include the meteorological conditions affecting the area under prescription, as well as factors related to the state of the area to be burned such as the fuel moisture condition and other physical parameters. Other criteria which may be considered include safety, economic, public health, environmental, geographic, administrative, social or legal considerations, and ecological and land use objectives.

Prevention of Significant Deterioration (PSD) -- A requirement in the Clean Air Act, which establishes the maximum allowable increases in ambient air concentrations of selected air pollutants above baseline concentrations in areas designated as Class I, Class II, or Class III.

prescribed fire – Any fire ignited by management actions to meet specific objectives. For federal agencies a written, approved prescribed fire plan must exist, and NEPA requirements (where applicable) must be met, prior to ignition.

sensitive populations – Those populations to which smoke emissions may present particular health risks.

sensitive receptors – Locations where human population tend to concentrate and where smoke could impact the health of those populations or significantly impact visibility that may be detrimental to either health or the enjoyment of scenic qualities of the landscape. These may be residential concentrations in the form of towns or cities, or locations where people tend gather in groups such as parks. Travel routes such as highways may be labeled as sensitive receptor sites where smoke can be a factor in potential motor vehicle accidents. Particular areas along highways or other locations may be more prone to being declared sensitive receptor sites because of topographic and microclimate features. (*i.e., Population centers such as towns and villages, camp grounds and trails, hospitals, nursing homes, schools, roads, airports, mandatory Class I Federal areas, etc. where smoke and air pollutants can adversely affect public health, safety and welfare.*)

smoke management best management practices – Establish a basic framework of procedures and requirements for managing smoke from fires that are managed for resource benefits. The purpose of these best management practices are to mitigate the health, nuisance and public safety hazards (e.g., on roadways and at airports) posed by smoke intrusions into populated areas; to prevent deterioration of air quality and NAAQS violations; and to address visibility impacts in mandatory Class I Federal areas in accordance with the regional haze rules.

source – Any place or object from which pollutants are released, such as power plants, factories, dry cleaners, gas stations, farms, motor and consumer products.

State Implementation Plan (SIP) – State implementation plans are collections of the regulations and emission reduction measures used by a state to reduce air *pollution* in order to attain and maintain NAAQS or

Wisconsin Regional Haze State Implementation Plan for the Second Implementation Period

to meet other requirements of the Clean Air Act. The Clean Air Act requires that EPA approve each state implementation plan.

Violation of the PM NAAQS – As revised in 2006, the daily PM₁₀ standard is violated when the 99th percentile of the distribution of 24-hour concentrations for a period of 1 year (averaged over 3 calendar years) exceeds 150 µg/m³ at any monitor within an area. PM_{2.5} are set at a daily concentration less than or equal to 35 µg/m³, and an annual mean concentration of less than or equal to 15 µg/m³. For PM_{2.5} the daily standard is violated when the 98th percentile of the distribution of the 24-hour concentrations for a period of 1 year (averaged over 3 calendar years) exceed 35 µg/m³ at any monitor within an area. The annual standard is violated when the annual arithmetic mean of the 24-hour concentrations from a network of one or more population-oriented monitors (averaged over 3 calendar years) exceeds 15 µg/m³.

wildfire – An unplanned and unwanted wildland fire including unauthorized human-caused fire, escaped prescribed fire, and all other wildland fires where the objective is to put the fire out.

wildland fire – Any non-structural fire that occurs in the wildland. Two distinct types of wildland fire have been defined in Wisconsin and include wildfire and prescribed fire.

LITERATURE CITED

- Anderson, G.K., Sandberg, D.V., Norheim, R. 2004. Fire Emissions Production Simulator (FEPS) User's Guide ver. 1. USDA Pacific Northwest Research Station, Fire and Environmental Research Applications team. Seattle, WA
- Anderson, H.E. 1982. Aids in Determining Fuel Models for Estimating Fire Behavior. Gen. Tech. Rep. INT-122. Fort Collins, CO.
- Curtis, J.T. 1959. The Vegetation of Wisconsin: An Ordination of Plant Communities. Univ. of Wisconsin Press. Madison, WI
- Dorney, J. R. 1981. The Impact of Native Americans on Pre-settlement Vegetation in Southeastern Wisconsin. Wisconsin Academy of Sciences, 69: 26-36.
- Dorney, C.H., Dorney, J.R. 1989. An Unusual Oak Savanna in Northeastern Wisconsin: The Effect of Indian-Caused Fire. American Midland Naturalist, 122(1): 103-113.
- EPA. 1998. Interim air quality policy on wildland and prescribed fires. Office of Air Quality Planning and Standards, Research Triangle Park, NC 27711.
- Michigan DNR. 2006. Michigan Smoke Management Program.
- MN ICS. 2007. Minnesota Smoke Management Plan.
- National Wildfire Coordination Group. 2001. Smoke Management Guide for Prescribed and Wildland Fire. PMS 420-2. Boise, ID.
- National Wildfire Coordination Group. 2003. Smoke Management Techniques Instructor Guide, Course RX-410. NFES 2475, Boise, ID
- Ottmar, R. D., and R. E. Vihnanek. 1999. Stereo photo series for quantifying natural fuels. Volume V: Midwest Red and White Pine, Northern Tallgrass Prairie, and Mixed Oak Types in the Central and Lake States. PMS 834. Boise, ID.
- Peterson, J., and B. Leenhouts. 1997. What wildland fire conditions minimize emissions and hazardous air pollutants and can land management goals still be met? (Unpublished support document to the EPA Interim Air Quality Policy on Wildland and Prescribed Fires. August 15, 1997.)
- Sandberg, D.V., Ottmar, R.D., Peterson, J.L., and Core, J. 2002. Wildland fire on ecosystems: effects of fire on air. Gen. Tech. Rep. RMRS-GTR-42-vol. 5. Ogden, UT.
- Scott, J.H., Burgan, R.E. 2005. Standard fire behavior fuel models: a comprehensive set for use with Rothermel's surface spread model. Gen. Tech. Rep. RMRS-GTR-153. Fort Collins, CO.

Appendix A
Principle Contacts for Wisconsin Smoke Management Plan

Michele Witecha

Prescribed Fire Specialist
Wisconsin Department of Natural Resources
Division of Forestry
101 S. Webster St.
PO Box 7921
Madison, WI 53707-7921
(608) 333-3664
michele.witecha@wisconsin.gov

Katie Praedel

Air Monitoring Section Chief
Wisconsin Department of Natural Resources
Division of Environmental Management
101 S. Webster Street
PO Box 7921
Madison, WI 53707-7921
(608) 259-6108
katie.praedel@wisconsin.gov

Lee Jensen

Fire & Aviation Staff Officer
US Forest Service
Chequamegon-Nicolet National Forest
500 Hanson Lake Road
Rhineland, WI 54501-9437
(715) 362-1300
Lee.f.jensen@usda.gov

Steve Bertjens

State Biologist
Natural Resources Conservation Service
8030 Excelsior Drive, Suite 200
Madison, WI 53717
(608) 662-4422 ext 267
steve.bertjens@wi.usda.gov

Paul Mancuso

Fuels Management Specialist
National Park Service
Midwest Regional Office
601 Riverfront Drive
Omaha, NE 68102
(402) 661-1758
Paul_mancuso@nps.gov

Dan Laber

Zone 3 Fire Management Officer
US Fish and Wildlife Service
N11385 Headquarters Road
Necedah, WI 54646
(608) 565-2551
daniel_laber@fws.gov

Marty Cassellius

Regional Fuels Specialist
Bureau of Indian Affairs
5600 American Boulevard West
Bloomington, MN 55437
(612) 725-4523
marty.cassellius@bia.gov

James Kerkman

Forester
Fort McCoy
The Department of Defense
Fort McCoy, WI 54656
(608) 388-2102
james.r.kerkman.civ@mail.mil

Hannah Spaul

Conservancy Land Steward
The Nature Conservancy
633 West Main Street
Madison, WI 53703
(608) 316-6431
hspaul@tnc.org

Appendix B

Basis for Developing Smoke Management Best Management Practices

The purposes of the Smoke Management Plan (SMP) and its accompanying best management practices are directly related to the mitigation of any public health, nuisance and safety hazards posed by smoke intrusions into populated areas and roadways. The goals are to prevent deterioration of air quality and National Ambient Air Quality Standards (NAAQS) violations, and address visibility impacts on mandatory Class 1 Federal areas. The NAAQS referred to here are for particulate matter (PM) less than 2.5 microns (PM_{2.5}) and PM less than 10 microns (PM₁₀) in diameter.

The reasons the SMP is being developed for Wisconsin are:

1. There has been an increase in the use of prescribed fire in Wisconsin.

Table A1 identifies a trend of increased use of prescribed fire in Wisconsin. This follows a nationwide trend identified by federal and state land managers. This increase of prescribed fire has strong ecosystem and landscape management implications to increase biodiversity and productivity.

2. To utilize a voluntary program to prevent PM NAAQS violations related to emissions from prescribed fire managed for resource benefits.

Implementation of the smoke management best management practices by land management agencies, should reduce potential emissions and smoke impacts from prescribed fires so that emissions do not result in “non-attainment” status with NAAQS and state air quality standards. The EPA Interim Guidance document explains that states which implement a certified SMP and do not violate the PM₁₀ or PM_{2.5} standards will not have areas designed as “non-attainment”, if the State demonstrates that prescribed and/or wildland fire significantly contributed to the concentration of pollutants that exceeded the standards. This incentive by the EPA for implementation of a Smoke Management Plan is important if an area of the state were to violate the air quality standards due to smoke produced by prescribed burning.

3. The EPA Regional Haze Rule, which aims to protect and improve visibility in mandatory Class I areas.

Section 169A of the Clean Air Act Amendments (CAAA) of 1977 sets forth “the national goal of preventing any future, and remedying any existing, impairment of visibility in mandatory Class I Federal areas which impairment results from man-made air pollution.” The EPA rules issued in 1980 included language directed at those sources “reasonably attributable” to visibility impairment. With the addition of section 169B of the CAAA of 1990, congress addressed “regional haze” visibility impairment in the nation’s national parks and wilderness areas. The EPA determined that all 156 listed mandatory Class I areas across the nation demonstrate impaired visibility based on monitoring data from the Interagency Monitoring of Protected Visual Environments (IMPROVE). Within Wisconsin this includes Forest County Potawatomi Community; neighboring Class 1 areas include Seney National Wildlife Refuge and Isle Royale National Park in Michigan, and Voyageurs National Park and Boundary Waters Canoe Area Wilderness in Minnesota. For the Class I areas, in Minnesota and Michigan, smoke from Wisconsin prescribed fires have not been shown to be a significant contributor to visibility impairment.

EPA published their final Regional Haze Rule on July 1, 1999 (64FR35714). This rule is directed at man-made air pollution sources that have the potential to cause or contribute to visibility impairment including: 1) stationary sources (industry), 2) mobile sources (vehicles), 3) area sources (gas stations, dry cleaners, etc.), and 4) the use of managed fire. Of the pollutants most responsible for haze (nitrates, sulfates, soil material, organic carbon, and elemental carbon), nitrates, organic carbon and elemental carbon are produced by vegetative burning. The regional haze program goal is to show continued improvement in monitored visibility in Class 1 areas and restore natural background conditions by 2064.

Appendix C

Smoke Production and Dispersion

Overview and Definition of Smoke Dispersion

Information pertaining to smoke dispersion is an important element of a prescribed burn plan. Mixing height is defined as the upper limit of an unstable mixed layer, in which upward and downward exchange of air occurs. In theory, the mixing height represents the level that smoke will rise to before spreading out horizontally. Transport wind is defined as the arithmetic average of the wind speed and direction within the mixed layer. Transport wind should provide a basic estimate of the movement of the smoke column as it travels out of the source region.

Climate Factors that Influence Smoke Dispersion in Wisconsin

Wisconsin resides in the humid continental climate region, due to its interior location in the mid-latitudes of North America. The state lies in the boundary zone between many different air masses, including those of polar and tropical origin. As a result, Wisconsin experiences highly variable weather conditions and large seasonal changes in temperature. Weather conditions are most variable during the spring and fall months, when the jet stream migrates across the Great Lakes, resulting in strong storm systems tracking through the region. Lake Superior and Lake Michigan strongly influence local weather conditions near their respective shorelines in northwest and eastern Wisconsin.

Here are some more detailed explanations of the various factors that influence smoke dispersion potential in Wisconsin:

Air Masses and Frontal Systems are the main factors that influence day-to-day variations in smoke dispersion. There are five different types of air masses that affect the United States, including continental polar, continental arctic, continental tropical, maritime polar and maritime tropical. Wisconsin can be affected by all of these air masses during the course of a fire season, but is most commonly affected by continental polar, maritime polar and maritime tropical air masses. Continental polar air masses, which arrive from northern Canada, are usually cool, dry and stable, and sometimes result in low mixing heights and poor smoke dispersion due to the presence of a subsidence inversion. Maritime polar air masses form over the northern Pacific Ocean region, where they take on their typical cool, moist and unstable characteristics. However, these air masses usually lose most of their moisture as they ascend the west slopes of the Rocky Mountains, and warm as they descend the east slopes. By the time they arrive in Wisconsin, they are usually dry, mild and unstable. As a result, mixing heights are typically quite high in air masses of Pacific origin. Maritime tropical air masses, which originate from the Gulf of Mexico, are usually warm, moist and unstable.

Frontal systems can also have a significant effect on smoke dispersion. Cold fronts are usually accompanied by windy and unstable conditions, which provide for excellent smoke dispersion. Conditions are quite variable with warm fronts, with stable conditions and poor smoke dispersion expected north of the front, and unstable and windy conditions to the south.

Latitude, which controls the sun angle and length of the day, is responsible for seasonal temperature contrasts. Mid-latitude locations such as Wisconsin experience sharp changes in seasonal temperatures due to widely varying sun angle and day length. These temperature changes can significantly impact smoke dispersion. For example, mixing heights are typically lowest during the winter months, since daytime heating is limited due to low sun angle, short day length and snow-covered ground. During the spring and summer, increased solar heating due to a high sun angle and longer day length is usually sufficient to mix out low level inversions, resulting in higher mixing heights and more effective smoke dispersion.

Lake Superior and Lake Michigan have a significant impact on smoke dispersion, especially during the spring and summer months. Lake breezes, which frequently develop in northwest and eastern Wisconsin from April through August, often result in poor smoke dispersion near the lakeshore. Lake breezes typically form during the late morning or early afternoon, become strongest during the mid to late afternoon, then weaken by early evening. On most days, the lake breeze front will only push inland 5 to 10 miles, but in extreme cases, may move inland 50 miles or more. Stable conditions develop as the cooler marine air penetrates inland, forcing warmer air aloft. In addition to smoke dispersion concerns, shifting winds associated with a lake breeze front can occasionally cause fire control problems.

Upper Level Disturbances, also known as upper level troughs of low pressure, often result in improved smoke dispersion as they pass through the western Great Lakes region. These disturbances, which are usually accompanied by pockets of cold air aloft, often produce windy and unstable conditions, and help to generate large scale rising motion in the atmosphere.

Weather Patterns that Affect Smoke Dispersion in Wisconsin

Wisconsin usually receives good ventilation throughout most of the fire season. During the months of April through October, solar radiation is usually strong enough to either mix out or lift inversions that are near the surface. However, there are some typical seasonal weather patterns that cause smoke dispersion problems.

- During the early spring and late fall, strong Canadian high pressure systems often sag into the northern Great Lakes region and persist for several days. These Canadian highs typically have strong subsidence inversions, which gradually lower toward the surface, leading to poor smoke dispersal. Ventilation is especially poor when widespread low clouds (stratus) are present. The low clouds typically form in two ways; either due to low level east winds affecting marine moisture off of Lake Michigan, or due to the presence of a warm front over Iowa and northern Illinois, which lifts warm, moist air from the Gulf of Mexico over the top of the cooler Canadian air mass. The poor smoke dispersal is the net result of low mixing heights (generally 1,000-2,000 feet) and light winds.
- Persistent (lasting up to a week or more) summertime high pressure systems accompanied by a large blocking ridge of high pressure aloft can produce significant smoke dispersion problems. Although daytime mixing heights are often sufficiently high, transport winds are typically too light to support efficient smoke dispersion. The stagnant conditions eventually lead to reduced visibility and poor air quality, especially during the nighttime and early morning hours, when smoke particles aloft fall back to the surface.
- Radiation inversions (also known as nocturnal inversions), which develop as the earth's surface cools at night, can trap smoke near the ground during the nighttime and morning hours. Radiation inversions can occur throughout the year, and typically form on nights when skies are clear and winds are light. Summertime radiation inversions tend to be shallower, and usually mix out earlier in the morning, than those that develop during the spring and fall.
- Inland intrusions of cool, stable marine air associated with lake breeze fronts (or persistent onshore winds) can significantly hinder smoke dispersion during the spring and summer months. Lake breeze fronts are most common on days when winds at the surface and aloft are light. Lake breezes that develop near Lake Superior in northwest Wisconsin typically have a northerly component to their wind direction, while those that develop near Lake Michigan (and the bay of Green Bay) have an easterly component. Although a lake breeze front will typically remain within 5 to 10 miles of the lake during the early to mid-afternoon, they can occasionally penetrate well inland (50 miles or more) before weakening during the late afternoon or early evening hours.

Appendix D

Guidance for Use of the Ventilation Index and Dispersion Tables

Smoke dispersion is directly related to ventilation, which is the process within the atmosphere that mixes and transports smoke away from its source. Ventilation is a function of atmospheric stability, mixing height and transport winds.

Just as various indices are used to estimate fire behavior, a ventilation index has been developed to estimate the lower atmosphere's ability to diffuse and disperse smoke. The Ventilation Index (also known as the Dispersion Index) is calculated by multiplying the mixing height (feet) by the transport wind (knots). A high Ventilation Index usually means that smoke will disperse in an efficient manner. A low Ventilation Index usually means that the dispersion of smoke in the lower atmosphere will be hindered. Caution should be used when interpreting the Ventilation Index, as the values can sometimes be misleading. For instance, a high Ventilation Index can be produced with either a high transport wind and low mixing height or a low transport wind and high mixing height. In both situations, smoke dispersion may still be hindered.

Dispersion Rate	Dispersion Index
<13,000	Poor
13,000 - 29,999	Fair
30,000 - 59,999	Good
60,000 or greater	Excellent

Table D1 - Ventilation (Dispersion) Index

Smoke dispersion information is available on the Fire Weather Planning Forecast (FWF), which is issued twice daily during the fire season at 7 am and 3 pm. Average mixing height and transport wind for the noon to 6 pm period are provided for the daytime periods (through day 2) in the Fire Weather Planning Forecast. The Ventilation Index, which is labeled as *smoke dispersal* in the FWF, is also averaged between noon and 6 pm, and is provided for the daytime periods of the forecast through day 2. Average values are used in order to provide a more representative estimate for prescribed burn projects, which may be started at varying times of the day (depending on the agency, type and size of the project). Fire Weather Planning Forecasts are posted on all local National Weather Service (NWS) websites. Smoke dispersion forecasts are also available as part of a spot forecast request.

When utilizing the ventilation index it is important to consider the total fuel load being burned, both in terms of the fuel loading (tons of fuel per acre) and the total area to be treated. The proximity of downwind smoke sensitive areas to the burn unit should also be considered, so that in general the lower the expected total fuel consumption and the farther away from smoke sensitive receptors, the lower the ventilation index can be. Additionally, practices that reduce the total fuel load available for consumption can lower the acceptable dispersion category either by reduction of fuel, or acres to be treated.

Identifying the Closest Smoke-sensitive Receptors

1. Locate on a map the prescribed fire and all potential smoke sensitive targets, plus areas known to already have air pollution problems.
2. Determine the wind direction that should have the least impact on smoke sensitive targets.
3. Draw a line representing the centerline of the path of the smoke plume using the wind direction chosen in the previous step.
4. Determine the distance from the edge of the prescribed fire to the nearest smoke-sensitive target.

Wisconsin Regional Haze State Implementation Plan for the Second Implementation Period

5. To allow for horizontal dispersion of the smoke, as well as shifts in wind direction, draw two other lines from the burn at an angle of 30 degrees from the centerline.




Figure D1 – Smoke Plotter (NWCG RX 410)

Once smoke-sensitive receptors have been identified, there are two methods that can be utilized for mitigation of smoke impacts during the burn planning process:

Method A: This method may be used as a general guide to use the Ventilation Index in combination with a smoke screening map to screen for sensitive downwind receptors. It is recommended for those burn units with low to moderate potential for smoke impacts.

1. From the Daily Burn Unit Size chart (Table D2) select the size of the planned burn unit* in acres.
2. Determine the general fuel category which best represents the majority of the burn unit.
3. On a map of the area locate the sensitive downwind receptors that could be impacted by smoke produced by the burn unit.
4. Use the Dispersion Category charts (Table D3) and determine the minimum distance which a burn should take place upwind of a sensitive receptor on a certain Dispersion Category day.

*Note: These are voluntary guidelines which may vary based on the local unit's definition of smoke sensitive receptor and the ability to mitigate potential smoke problems by instituting traffic controls when smoke could impact major roads or by burning under fuel moisture conditions which limit consumption of heavier fuels.

Method B: This is recommended for complex prescribed burns with is high potential for smoke impacts.

1. Estimate the fuel loading for the area to be burned. This may be done formally, utilizing site-specific survey data if available or by consulting the fuel model information found in: [Aids in Determining Fuel Models for Estimating Fire Behavior](#), or [Standard Fire Behavior: A Comprehensive Set for Use with Rothermel's Surface Spread Model](#) or the [Natural Fuels Photo Series](#).
2. Determine the acreage to be burned in one day.
3. Estimate the expected fuel consumption using hand calculations or computer models such as FOFEM or CONSUME. Selection of higher fuel moistures (such as higher 100- and 1,000-hour fuel moisture), which should reduce the fuel available for consumption, should be factored into the calculations.
4. Determine the total PM₁₀ and PM_{2.5} emissions per day based on outputs from #3.
5. Locate downwind sensitive receptors that could be impacted from your smoke.
6. Utilize a dispersion computer program to screen for the potential to exceed ambient air quality

standards.

Daily Burn Unit Sizes	
Small	<50 acres
Medium	50 - 150 acres
Large	151 - 500 acres
Landscape	501 + acres

Table D2 – Daily Burn Unit Sizes

DISPERSION CATEGORY	PROXIMITY OF CLOSEST DOWNWIND SMOKE-SENSITIVE AREAS	DESCRIPTION OF UNIT SIZE AND AVAILABLE FUEL LOAD
EXCELLENT	<0.25 mile	Small – Large burns in grass or leaf litter
	<0.25 mile	Small – Med burns in timber, slash, or piled fuels
	>0.25 mile	Landscape burns in grass or leaf litter
	>0.25 mile	Large burns in timber, slash, or piled fuels
	>0.5 mile	Landscape burns in timber, slash, or piled fuels
GOOD	<0.25 mile	Small – Large burns in grass or leaf litter
	<0.25 mile	Small – Med burns in timber, slash, or piled fuels
	>0.5 mile	Landscape burns in grass or leaf litter
	>0.5 mile	Large burns in timber, slash, or piled fuels
	>0.75 miles	Landscape burns in timber, slash or piled fuels
FAIR	<0.25 mile	Small – Med burns in grass or leaf litter
	>0.25 mile	Large burns in grass or leaf litter
	>.5 mile	Small – Med burns in timber, slash, or piled fuels
	>0.75 mile	Landscape burns in grass or leaf litter
	>0.75 miles	Large burns in timber, slash or piled fuels
	>1.0 mile	Landscape burns in timber, slash, or piled fuels
POOR*	< 0.25 mile	No burns
	>0.50 mile	Small burns of primarily grass fuels.
	>1.00 mile	Single large pile or scattered small piled debris

Table D3 – Distances to Smoke-sensitive Areas

*On Poor Category days no burning is suggested within ¼ mile of any downwind smoke sensitive area and is not recommended in general. As an example, for a 500 acre burn in grass fuels, a minimum distance that a burn should occur upwind of a sensitive receptor would be: greater than 0.25 miles with Excellent Dispersion, greater than 0.5 mile with Good Dispersion, greater than 0.75 miles with Fair Dispersion and there should be no burn under Poor Dispersion.